

#### **POTENTIAL ENERGY**

Often the work done on a system of two or more objects does not change the kinetic energy of the system but instead it is stored as a new type of energy called POTENTIAL ENERGY. To demonstrate this new type of energy let's consider the following situation.

**<u>Ex</u>**. Consider lifting a block of mass 'm' through a vertical height 'h' by a force **F**.




### System = Block



$$\begin{aligned} W_{net} &= \Delta K \\ \Delta K &= 0 \text{ (since } v_i = v_f = 0) \\ W_{net} &= W_F + W_g = 0 \\ W_F &= -W_g = -mgh\cos 180^o \\ \hline W_F &= mgh \end{aligned}$$


#### System = block + earth



Clearly the work done by  $\mathbf{F}_{app}$  is not zero and there is no change in KE of the system. Where has the work gone into? Because recall that positive work means energy transfer into the system. Where did the energy go into? The work done by  $\mathbf{F}_{ext}$  must show up as an increase in the energy of the system.

The work done by  $F_{\text{ext}}$  ends up stored as **POTENTIAL ENERGY** (gravitational) in the Earth-Block System. This potential energy has the "potential" to be recovered in the form of kinetic energy if the block is released.

#### Ex. Spring-Mass System



$$W_{net} = \Delta K$$

$$\Delta K = 0 \text{ (Since } v_i = v_f = 0)$$

$$W_{net} = W_{F} + W_N + W_{mg} + W_F$$

$$W_{net} = W_F = -W_s$$

$$w_s = \frac{1}{2}k_i^2 - \frac{1}{2}k_f^2$$

$$w_F = -w_s = \frac{1}{2}k_f^2 - \frac{1}{2}k_i^2$$

The work done by  $F_{app}$  ends up stored as POTENTIAL ENERGY (elastic) in the Spring-Mass System.

<u>Potential Energy</u> - Energy associated with the configuration of a system involving two or more objects. It is a shared property of the objects making up the system.

Before we define the potential energy function mathematically, we need to define a conservative force.

#### **Conservative Forces**

Conservative forces are very important because as we will see they imply conservation of energy for an isolated system. With every conservative force there is a potential energy function associated with that force.


A conservative force has the following two equivalent definitions:

**Def 1**: A force is conservative if the work done by that force is path independent.

**<u>Def 2</u>**:The work done by a conservative force around any closed path is zero.

Consider a particle acted on by a conservative force between two points *a* and *b* along two different paths.


3




$$W_{ab(1)} = W_{ab(2)}$$

$$W_{ab(1)} + W_{ba(2)} = 0 \Longrightarrow W_{ab(1)} = -W_{ba(2)}$$

As examples of conservative forces let's see if the gravitational force and spring force are conservative.





# **Gravitational Potential Energy Function**

Since Ws is path independent, then For-KX is a conservative force.

$$\begin{split} W_g &= mgy_i - mgy_f \\ \boxed{U_g &= mgy} \text{ Gravitational Potential Energy Function} \\ W_g &= U_i - U_f = -(U_f - U_i) \\ \text{(1)} \boxed{W_g = -\Delta U_g} \end{split}$$

#### **Elastic Potential Energy Function**

$$\begin{split} W_s &= \frac{1}{2}kx_i^2 - \frac{1}{2}kx_f^2 \\ \hline U_s &= \frac{1}{2}kx^2 \end{split} \text{ Elastic Potential Energy Function} \\ W_s &= U_i - U_f = -(U_f - U_i) \\ \text{(2)} \ \overline{W_s = -\Delta U_s} \end{split}$$

Note from equation (1) and (2) that only changes in potential energy have a physical significance!


- a) For the gravitational PE function we may choose the reference value of  $U_q = mgy = 0$  at any convenient reference point.
- b) For the elastic PE function,  $U_s = 0$  only when x = 0.

Equation (1) and (2) above are general for a conservative force and the corresponding potential energy function.

$$V = 0$$
,  $V = 5m - 100$   $V = (100)(9.8)(5m) = 49J$ ,  $V = (100)(9.8)(5m) = 49J$ ,  $V = 0 = 0$ ,  $V = 0$ ,  $V$ 

## **Conservation of Mechanical Energy**

Consider a system of particles that interact with each other only by internal conservative forces. Suppose such system is also subject to external forces.



From the Work-Energy Theorem we have:

$$\begin{split} W_{net} &= \Delta K_{sys} \\ W_{ext} + W_{\text{int}} &= \Delta K_{sys} \\ W_{ext} + W_c &= \Delta K_{sys} \qquad (W_c = -\Delta U_{sys}) \\ W_{ext} - \Delta U_{sys} &= \Delta K_{sys} \\ (1) \boxed{W_{ext} = \Delta K_{sys} + \Delta U_{sys}} \end{split}$$

<u>Isolated System</u> - A system in which there are no energy transfers across its boundary and the net external forces acting on it is zero.

For an isolated system we have that  $W_{\rm \it ext} = 0$  . Therefore,

$$0 = \Delta K_{sys} + \Delta U_{sys}$$
$$K_f - K_i + U_f - U_i = 0$$

$$K_i + U_i = K_f + U_f$$
 Conservation of Mechanical Energy

$$\boxed{E_{\scriptscriptstyle mech} = K + U}$$
 Total Mechanical Energy

$$\begin{bmatrix} E_i = E_f \\ \Delta E_{mech} = E_f - E_i = 0 \\ E_{mech} = K + U = \text{constant} \end{bmatrix}$$
 Conservation of Mechanical Energy

In an isolated system where only conservative forces do work on a system, the Total Mechanical Energy of system remains constant!